OMNIBUS 2.0 – Quick Start User Guide

Contents

1.	What is OMNIBUS?					
2.		nical Specifications				
3.	Insta	lling and uninstalling OMNIBUS				
4.	Prod	uct Authorization				
5.	Understanding the User Interface					
	5.1.	OMNIBUS UI				
	5.2.	Audio devices				
	5.3.	View				
	5.4.	Settings				
	5.5.	Snapshots				
6.	Getti	ng Started with OMNIBUS				
	6.1.	Begin routing audio				
	6.2.	Outputting audio sources				
	6.3.	Saving routing configurations				
	6.4.	OMNIBUS x LISTENTO app				

<u>3</u>456 8 9 10 11 12 <u>14</u> <u>15</u> <u>16</u> <u>17</u>

UNINTERRUPTE

Ν


1. What is OMNIBUS?

V

OMNIBUS is software built by Audiomovers which makes routing multiple audio sources easy. It's a powerful tool with almost endless applications. It's like a swiss army knife or virtual patchbay for all of your audio devices and software.

- Seamlessly send and receive audio between applications
- 4 built-in virtual drivers,
 - OMNIBUS A&B: 16 channels I/O
 - OMNIBUS C: 32 channels I/O
 - OMNIBUS D: 64 channels I/O
- Combine multiple audio sources and send to software

OMNIBUS. Audio routing made easy.



OMNIBUS is akin to a virtual patchbay for your Mac, allowing you to patch between all the audio devices and software on your machine.

2. Technical specifications

N

- Minimum system requirements: Mac OS X 10.15.7 or higher. Mac hardware released post 2018
- Supported sample rates: 44.1 192 kHz
- Virtual device channels: Up to 64 Channels
- Number of OMNIBUS devices: 4 devices
- Physical output device channels: Up to 64 channels
- Max number of physical devices: Unlimited

Ν

Use the Omnibus Installer in order to install Omnibus to your system . Follow the prompts on Installer to finish with the installation. You will need to restart your machine to complete installation.

Software Installation location

Mac OS X /Applications/Omnibus /Library/Audio/Plug-Ins/HAL/Audiomovers.Omnibus.driver

Uninstalling OMNIBUS To uninstall Omnibus, run the Omnibus Uninstaller. Download it from the Downloads section on audiomovers.com website

V

4. Product authorization

In order to begin using Omnibus, you must first authorize it with your Audiomovers account.

You can create an account on audiomovers.com

You will be prompted with the authorization dialog when you attempt to run the software the first time.

Each license can be authorized on up to 5 machines.

When Omnibus is not authorized, all audio routes which were made previously will be muted.

We also offer a '7 Day trial' - this is a one-time-only trial period given to new accounts.

The trial license can be authorized on one machine only.

1.	OMNIBUS OMNIBUS Authorization required Authorize or start free trial online Start Free Trial Authorize Cancel
2.	MNIBUS OMNIBUS Authorizing, please continue in a browser Exit
3.	Choose a product to authorize Omnibus (2 out of 10) AUTHORIZE BACK TO MY ACCOUNT
4.	OMNIBUS OMNIBUS Authorized Successfully! OK

Understanding the User Interface

5. Understanding the User Interface




V

5. Understanding the UI 1. Device List

On the left of the OMNIBUS UI you will find the device list. The device list shows all audio devices connected to your Mac including virtual and hardware devices.

Each device will have a mute button, volume slider, shortcut to device in audio/midi setup, hide/show audio device toggle and the option to disable audio devices to save on CPU usage.

- 1. Audio device module
- 2. Input/output level sliders & mute toggle
- 3. Audio device navigation
- 4. Hide/disable audio device
- 5. Shortcut to device in audio MIDI setup
- 6. OMNIBUS device naming (double click to rename)




Please note: Omnibus will always continue running in the background

NUDIOMOVERS

5. Understanding the UI 2. View

View settings allow you to zoom your view of OMNIBUS in or out, as well as having the option to hide the OMNIBUS routing matrix.

The always on top feature will keep OMNIBUS always in view on your screen/monitor



Please note: Omnibus will always continue running in the background


NUDIOMOVERS

Ν

5. Understanding the UI 3. Settings

OMNIBUS now has an improved settings view on the left of the UI allowing you to adjust your settings easily. These settings include:

- 1. Sample rate selector: choose from between 44.1-192kHz
- 2. Buffer size: choose between 32-2048
- 3. Run at startup/Turn off audio engine when app is not on
- 4. Visibility settings: Toggle colours for audio devices & Toggle connection lines
- 5. Lock OMNIBUS devices' level controls
- 6. Clear all custom channel names & routing configurations



Please note: Omnibus will always continue running in the background

5. Understanding the UI 4. Snapshots

You can save your routing configurations as snapshot for later use.

You can have up to 100 snapshots saved simultaneously.

You can label your snapshots and assign them to up to 9 hot keys (CMD 1-9) to switch between routing configurations with ease.

You can also switch between snapshots by using the arrows next to the save button.

- 1. Snapshot settings:
 - a. Delete Snapshot
 - b. Save Snapshot
 - c. Switch snapshots (up/down)
 - d. Select Snapshot
 - e. New Snapshot
- 2. Snapshot number (right click to assign hot key)
- 3. Selected snapshot (Highlighted purple)
- 4. Name Snapshot (double click on name to change)



Please note: You can only use hot keys when the app is open

NUDIOMOVERS

Getting started with OMNIBUS - Routing audio between applications

nal I/O Latency

ow Buffer Sizes

6. Getting started

1. Setting up your playback engine

To begin routing audio in OMNIBUS, you'll need to have audio passing through the OMNIBUS app.

You can begin this by setting your computer and/or DAW's audio playback engine to be one of the OMNIBUS virtual devices.

As you can see here, the Mac's audio player is OMNIBUS A whereas Pro Tools' playback engine is set to OMNIBUS B.

This means my DAW's audio will come from a separate source than my computer's audio

ound		Playback Er
••	Device	
Dutput	Playback Engine:	Omnibus B
MacBook Pro Speakers		
Dolby Audio Bridge	Settings	
the boild in the bridge	H/W Buffer Size:	
Inject IO	Video Engine:	Enable
Multi-Output Device	Optimizations ?	
Omnibus A		Ignore Errors During Pla
Omnibus B		May cause clicks and p
omnibus B		Main Playback
Omnibus C		Minimize A
Omnibus D		 Dynamic Plug-in Pr
Pro Tools Aggregate I/O		
in the receipting register for		🔲 Optimize Performat
Pro Tools Audio Bridge 2-A		
Pro Tools Audio Bridge 2-B		
Pro Tools Audio Bridge 6	Disk Playback	
	Cache Size:	
Pro Tools Audio Bridge 16		Lower values reduce m performance.
Pro Tools Audio Bridge 32		
Dro Toolo Audio Dridoo 64		
iound Preferences		

Please note: You can only use hot keys when the app is open

6. Getting started

2. Outputting audio sources


Once you've chosen your application or DAW's audio, you can now route to different output destinations.

Each block in the routing matrix corresponds to a audio source channel and an audio output destination channel.

In the image you will see the routing is Channel 1 from OMNIBUS A going into MacBook Pro Speakers channel 1.

As OMNIBUS A has been selected as the Macbook's audio engine, this routing will send the computers browser audio into the macbook pro speakers.

This could also be sent to any output destination channel on the device. This could be an audio interfaces output, Zoom's audio device, a Pro Tools bridge, Dolby Production Suite etc.



Please note: You can only use hot keys when the app is open


NUDIOMOVERS

6. Getting started

3. Saving Routing Configurations

Once you're happy with your routing, you can save this in the snapshots menu (see page 12)

Snapshots are a great way to reference your mixes as well as saving and switching between complex routing configurations.



Please note: You can only use hot keys when the app is open

6. Getting started4. OMNIBUS x LISTENTO app

V

OMNIBUS supports LISTENTO in many ways.

No DAW? No problem.

When using the LISTENTO standalone app, set OMNIBUS as your 'input' and send whatever audio sources—up to 16 channels and including immersive mixes up to 9.1.6—straight into LISTENTO.

Stream your audio directly from your computer to the world in lossless quality and at latency you define.

	Listento							
login	transmitter					recei		
0	Latency	0.1 sec 💌	Quality AAC 128	Kbps 💌				
A ************************************	(M	Session #	1603	-				
logout						paste link a	n	
C Remember me		top streaming	9 set session	password		Select	s	
my account forgot	mute				mute	audio device	•	
Listeners approval enabled	1	Input 1		LR	1	NONE		
Disable remote recorder	2	Input 1		LR	2	NONE		
Random session name on login	3	Input 1		LR	3	NONE		
🕙 2025-Jan-1 00:00:00	4	Input 1	$\overline{}$	LR	4	NONE		
Iondon03.audiomovers.com:443	5	Input 1		LR	5	NONE		
logged in	6	Input 1		LR	6	NONE		
logout to change settings	7	Input 1	$\overline{\mathbf{\nabla}}$	LR	7	NONE		
save load	8	Input 1	$\overline{\bigcirc}$	LR	8	NONE	-	
input: MacBook Pro Microphone 48 kHz	9	Input 1		LR	9	NONE	-	
output: MacBook Pro Microphone 48 kHz	10	Input 1		LR	10	NONE		
Allow All 🦺 3 of 10	11	Input 1		LR	11	NONE	-	
Disconnect Production Manager	12	Input 1		LR	12	NONE	-	
Disconnect Composer	13	Input 1		LR	13	NONE	-	
	14	Input 1		LR	14	NONE	-	
	15	Input 1	() ()	LR	15	NONE	=	
	16	Input 1			16	NONE	=	
		logout to add	d more channels		••• Sess			
	monit	oring —)		H	
Your name my name		1 🔍	R	2			5	

Have more questions about OMNIBUS or Audiomovers?

Head to the Help section on audiomovers.com

Alternatively, please contact us at contact@audiomovers.com

All product names, logos, and brands are property of their respective owners. All company, product and service names used in this guide are for identification purposes only.

Copyright © 2023 Audiomovers, All rights reserved.

NUDIOMOVERS

OMNIBUS Quick Start User Guide